




SESIA®

RIVA CAPE

Soft-line sweater enriched with an elegant pattern.
Light and refined, it drapes the silhouette with natural harmony and is perfect for a feminine, sophisticated look.

PALETTE AND YARN

PESCA
55% VISCOSE
45% COTTON




0051

DIFFICULTY: INTERMEDIATE

SIZE: 8/10

GAUGE AND FINISHED MEASUREMENTS

Worked in a diamond stitch
pattern with 12 mm needles



ABBREVIATIONS:

RS = right side of the work
WS = wrong side of the work
st(s) = stitch(es)
row(s) = row(s)
total height = total height
CO = cast on
col. = colour
k = knit
ch = chain

sl st = slip stitch
sc = single crochet
tog = together
BO = bind off (close stitches using the basic bind-off method)
rep. = repeat
p = purl
next = following
edge stitch (selvage)
hook = crochet hook

MATERIALS

PESCA by SESIA 100 g., 3 yarn balls col. 0051 (cream)

CIRCULAR NEEDLES: 12 mm needle tips, one medium-length cable and one long cable

CROCHET HOOK: n. 8

OTHER: Stitch holder cable with end stoppers, bodkin (tape needle), stitch markers, scissors, pins, measuring tape

WITH NEEDLES:

Garter stitch:

Work every row knit.

Diamond stitch (worked flat):

Worked over a multiple of 9 stitches, following the chart and repeating Rows 3–12 until the required length is reached.

Diamond stitch in the round:

Always follow the chart, keeping in mind that the even rounds are worked knit.

WITH CROCHET:

Chain stitch, slip stitch, single crochet, crab stitch (worked like single crochet, proceeding from left to right).

INSTRUCTIONS

NOTE: the garment is made of two identical panels (front and back), worked separately flat (back-and-forth rows) from the bottom upward. At 30 cm total height, the panels are joined and the work continues in the round.
In every row of each panel, keep the first and last 2 stitches as edge stitches:
work the first 2 stitches knit, and slip the last 2 stitches without working them, keeping the yarn in front.

PANEL (X2):

Using circular needles with the medium-length cable, cast on 58 stitches and for the lower border work 3 rows in garter stitch, keeping the first 2 and last 2 stitches as edge stitches.

Continue setting the work as follows:

2 edge stitches, 54 stitches in diamond stitch (6 repeats of the chart pattern), 2 edge stitches.

At 30 cm total height, leave the stitches on hold on a stitch holder cable.

Work the second panel in the same way.

UPPER SECTION OF THE CAPE:

Transfer the stitches of the two panels onto the circular needles, replacing the medium cable with the long cable.

Begin working across the stitches of both panels, maintaining the diamond stitch pattern, and work one decrease of 4 stitches on each of the two groups of 4 edge stitches positioned between the two diamond sections (front and back).

In this way the two panels are joined and the work continues in the round.

To make the work easier, place 1 stitch marker at the beginning of each round, moving it upward as the work progresses.


After joining, continue working diamond stitch in the round, based on 12 pattern repeats (6 for the front and 6 for the back).

At 48 cm total height, bind off all stitches.

Using the crochet hook, finish the neckline edge with 1 round of single crochet worked evenly, followed by 1 round of crab stitch.

Secure all yarn ends.

Chart: dimond stitch pattern



Key

- 1 knit
- 1 yarn over
- ⌘ k2tog = knit 2 stitches together
- ⌘ 1 ssk (simple slip decrease)
- ⌘ 1 double decrease = slip 1 stitch, knit 2 stitches together, pass the slipped stitch over the resulting stitch

Odd rows or rounds (RS) are read from right to left.
Even rows (WS), not shown in the chart, are worked purl.
Even rounds (RS), not shown in the chart, are worked knit.



[illegible]